

# © Charm Street Tablerunner

Finished Size: 16" x 36"

*You bought the charm pack. Now what? Make your own "charming" cobblestone street tablerunner. Will your street run past a bustling metro cafe? Maybe an idyllic country inn? How about a soft stroll along a flower garden? Your choice of charm packs will be the foundation for your building plan.*

*Now . . . Let's head down that street . . .*



## **Supplies Needed:**

34 Charm Squares each 5" x 5"  
1/3 yard fabric for binding  
5/8 yard backing (At least 20" x 40")  
Backing: 20" x 40"

\*A walking foot is recommended.

## **Construction:** All seam allowances are 1/4".

1. Cut each of the 34 charm squares into two pieces each 2 1/2" x 5" for a total of 68 "pavers".
2. Choose 8 of the 2 1/2" x 5" rectangles to become the "dead-ends" for your street. (The short pieces at the ends of every other strip)
3. Cut the 8 selected rectangles into eight 2 1/2" x 2 3/4" rectangles. (Discard the remaining 2 1/2" x 2 1/4" pieces to avoid confusion when assembling the runner.)
4. Arrange (60) 2 1/2" x 5" rectangles and the (8) 2 1/2" x 2 3/4" rectangles in 8 rows as shown in the diagram above. Rows #2, 4, 6, and 8 will have (8) 2 1/2" x 5" paver rectangles. Rows #1, 3, 5, and 7 will have (7) 2 1/2" x 5" pavers plus a 2 1/2" x 2 3/4" dead-end on each end of the row.
5. Sew the rectangles together end-to-end to form 8 rows.
6. This runner will now be quilted as you sew the rows together.
7. To prepare for quilting, lay the batting on the table. Layer the backing right sides up on top of the batting. Baste layers together using basting spray to create a "quilt sandwich".
8. Turn the quilt sandwich over so that the batting is on top. Draw a line down the length of the center of the batting using a marking pen.
9. Lay Row 4 right sides up on top the batting, aligning the right side of Row 4 with the line drawn on the batting.
10. Layer Row 5 right sides together with Row 4. Sew Row 4 and 5 together, sewing through the batting and backing as you sew the seam. Sewing with a walking foot will help to ease the layers of fabric and batting, preventing any "bumps in your road." Press seam towards Row 5, smoothing the row out on the batting.
11. Layer Row 6 right sides together with Row 5. Sew. Press seam towards Row 6.
12. Repeat process with Rows 7 and 8.
13. Begin process for remaining half of runner, sewing Row 3 to 4. Sew Row 2 to 3, then Row 1 to 2.
14. Trim batting and backing even with the edges of the runner.
15. Binding: Cut three strips 2 1/2" by the width of the fabric. Join the three strips together end to end. Fold strip in half lengthwise, press. Attach binding to runner, mitering corners.

Row Numbers							
1	2	3	4	5	6	7	8



© Prairie Point Junction, 2007  
124 East 8th \* Box 184 \* Cozad, NE 69130.  
308-784-2010 www.prairiepointjunction.com

